

BedBugEliteSM - Hotel Primary Room

Time of Service – 1 Hour

April 2016

BedBugEliteSM Hotel Primary Guest Room

Tools Required

Flashlight	Vacuum	Extension Cord
Towels	Utility Knife	Water-Soluble Bags
Sharpie	CrossFire	Drill
Disposable Gloves	Evergreen Dust	Eye Protection
Flat Head Screwdriver	Phillips Screwdriver	Washable Markers

**** PPE Required: Disposable Gloves – Eye Protection – Back Protection**

**** Bedbugs should be vacuumed (physically removed) when possible**

1. Prep Work
 - a. Bag all pillows – tie water-soluble bag(s) and place in bathroom (remove pillow cases from pillows, place pillow cases in bedding bags)
 - b. Bag all bedding – do not tie bag yet
2. Remove bed skirt from box springs, write (small) date and room number in washable marker on underside of bed skirt– place bed skirt in bag with bedding. Tie and place bag in bathroom.
3. Lay mattress back down on box springs. Treat mattress with **CrossFire**, apply only as a crack and crevice treatment to tufts, seams, and folds.
4. Treat sides of mattress with **CrossFire**.
5. Flip mattress – treat bottom tufts, seams, and folds of mattress with **CrossFire**.
6. Write date and room number in sharpie on mattress tag
7. Treat tufts, seams, and folds on top of box springs with **CrossFire**.
8. Treat sides of box springs with **CrossFire**.
9. Flip box springs over – treat edges of cheese cloth with **CrossFire**.

BedBugEliteSM - Hotel Primary Room

Time of Service – 1 Hour

April 2016

10. Remove cheese cloth from box springs and place in plastic bag, tie bag and place bag in bathroom.
11. Treat top of folded cloth with **CrossFire**.
12. Use **CrossFire** as a crack and crevice under cloth on box springs.
13. Treat box springs void with **CrossFire** – special attention to material folds and crevice.
14. Crack and crevice headboard & cleat with **CrossFire**.
15. Apply **CrossFire** to back side and bottom of headboard & cleat.
16. Use **Evergreen Dust** around all electrical / data outlets.
17. Apply **CrossFire** as a crack and crevice treatment to all moldings, closets, shelves, and picture frames.
18. Crack and crevice treatment - solid furniture and nightstands with **CrossFire**.
19. Use **CrossFire** on *upholstered furniture, baseboards, drapes, and carpet areas*.